Driver installation instructions for the Konica Digital Revio (KD-200, 210,310,400 series)

Plug in the supplied USB cable directly into the computer and then plug into the Konica Digital Revio camera. Turn on the camera and then the Windows computer should respond with a "*new hardware found*" message. If using Microsoft's Windows ME[™], Windows 2000[™] or Windows XP[™] (Home or Pro), then the installation will automatically proceed as the driver is built into these operating systems

If for some reason the Windows ME[™], Windows 2000[™] or Windows XP[™] installation **DOES NOT** proceed and you are located in the United States, then please call our technical support line at 1.888.7.KONICA during normal eastern business hours for assistance with the installation.

If Microsoft Windows[™] 98 is being used, then installation of the supplied driver is required as follows:

- a. Attach supplied USB cable to the USB port on the computer (do not plug into a USB hub).
- b. When the "Add New hardware wizard" appears. Click "Next".
- c. Select "Search for the best driver for your device." Click "Next".

d. Place a check mark next to "**specify a location**" and browse to the location of the downloaded drivers in the top level (or root) folder of the supplied CD or hard drive. Click "**Next**". At the following dialog box click "**Next**" to install the drivers.

e. After the eUSB MultiMedia Card Adapter drivers are installed, click "Finish".

The Konica Digital Revio camera will now be recognized in Windows as a "removable disk" drive in the "*My Computer*" window.

To install in a Mac OS 8.6 or OS 9.x system. Plug in the supplied USB cable into the MAC computer (do not plug into the USB connector on the keyboard) and then into the Konica Digital Revio camera. Turn on the camera and the MAC computer should respond by installing it's own built in driver. A removable disk icon will appear on the desktop.

Due to the lack of USB support for these operating systems from Microsoft, Windows NT[™], Windows 95[™], Windows 3.x[™] and Microsoft DOS[™] will <u>not</u> work with the Konica Digital Revio cameras.